

# Free Shipping Bar

for Magento 2



**Table of contents:**

Table of contents:.....2

Setting up the extension .....3

    General settings.....3

    Where to display.....4

    Content.....5

    Variables.....5

    Design.....6

Free Shipping Bar is an extension that helps to deliver relevant information to the customer:

- Variables for price difference calculation;
- Flexible in-store bar positioning;
- Multi-store support;
- Supports CSS and most popular Google fonts;
- Easy to setup.

The extension is straightforward in delivering information on when customers can expect fee shipping. The notification bar can be displayed at any store pages and set up to be displayed with the delay to let customers look through the page first.

Variables for cart total and difference between free shipping goal help creating personalized message and always provide relevant information on every cart update, urging customers to spend more to get free shipping.

The extension doesn't let you set up actual free shipping.

In order to set up free shipping options proceed to following sections:

**Store > Configuration > Sales > Shipping settings**

and

**Store > Configuration > Sales > Shipping methods**

## Setting up the extension

Free Shipping Bar extension is straightforward in it's setup. It introduces a single backend to **Content > Free Shipping Bar by Aheadworks > Settings**.

All extension settings and management options are represented in this very section.

### General settings

General settings control if extension is enabled, to which customer groups the bar is displayed and what is the free shipping goal.

Enabled  Yes

Customer Groups \* NOT LOGGED IN  
 General  
 Wholesale  
 Retailer

Free Shipping Goal \*   
 In base currency

General section comes with the following settings:

- **Enabled** – defines if extension is enabled;
- **Customer Groups** – allows selecting customer groups the free shipping bar is displayed to;
- **Free Shipping Goal** – defines the free shipping reference value, which is basically a shopping cart total, that should be reached.

### Where to display

In this section storeowner can decide on which pages of the store the free shipping bar is displayed.

**Where to Display** ⌵

**Pages**  ▼

**Layout Position**  ▼

**Display with delay after page load, seconds \***

0 - no delay

Where to display section comes with the following settings:

- **Pages** – defines at which pages the bar is displayed. Available options are:
  - *All pages;*
  - *Home page;*
  - *Catalog pages;*
  - *Product pages;*
  - *Shopping cart;*
  - *Checkout.*
- **Layout Position** – defines where exactly at the store pages the bar is displayed. Available options are:
  - *Page top;*
  - *Page top, fixed (sticky header);*
  - *Page bottom;*
  - *Page bottom, fixed (sticky footer);*
  - *Content top*
  - *Content bottom.*
- **Display with delay after page load, seconds** – defines the delay after which the bar is displayed.

## Content

Content section allows storeowner to set up the actual contents of the free shipping bar.

**Content**
⌵

**Content when cart is empty**

Store View	Message <span style="font-size: 0.8em;">?</span>	
All Store Views ▾	Free shipping on orders over {{ruleGoal}}	<a href="#">Delete</a>
<a href="#">Add</a>		

**Content when cart is not empty**

Store View	Message <span style="font-size: 0.8em;">?</span>	
All Store Views ▾	Only {{ruleGoalLeft}} left for free shipping	<a href="#">Delete</a>
<a href="#">Add</a>		

There are three states of the free shipping bar:

- A bar when customer's cart is empty;
- A bar when customer's cart is not empty, but the cart total is lower than the free shipping goal;
- A bar when free shipping goal is reached.

All three stages of free shipping bar can be edited and assigned to required store view.

## Variables

To get the most of the extension there are two variables that can be used in the bar message:

```
{{ruleGoal}}
```

This variable fetches the value of the **Free Shipping Goal** setting. Please note, that it doesn't fetch the actual value of the free shipping set up in **Store > Configuration > Sales > Shipping settings**.

```
{{ruleGoalLeft}}
```

This variable calculates difference between customer's **cart Total value** and **Free Shipping Goal** and displays the difference in the free shipping bar.

## Design

Design section allows adjusting the free shipping bar look and feel.

**Design** ⌵

**Font**  ▼  
Most popular Google Fonts are used.

**Font Size, px \***

**Font Weight**  ▼

**Font Color**   ▼

**Font Color of Goal**   ▼

**Background Color**   ▼

Design section comes with the settings that define font, font size, color and other free shipping bar message attributes.

Additionally, if required a custom CSS can be applied to the bar to make it fit the store custom theme.

For an in-depth look, visit Free Shipping Bar demo store at the extension's [product page](#).

Feel free to contact our support team with any questions:

[Submit a help desk ticket](#)

Call us:

US: +1 (646) 480 – 0154

UK: +44 (20) 8133 – 0154