

HOW TO INSTALL

Download the Extension and extract the ZIP and Upload the folder in APP/Code directory of your magento file system after the upload run the update command on SSH to get it installed When the Component is installed login to your admin panel and go to **SMS ALERT** -> Configuration from the left navigation

HOW TO SETUP

1. Enter SMS Alert Username

- Sign Up at www.smsalert.co.in Portal
- The Credentials you create will be the one that has to be inserted in these fields

2. Enter SMS Alert Password

- This will be the password of your Account you created at www.smsalert.co.in

Following is the configuration you need to setup for sending the SMS from SMS Alert on different situations

3. When Order is Placed

- If you wish to send SMS on Checkout this tab is for you click on the tab and insert the required message and sender ID.

4. When Order is Hold



When a New Order is Placed	3	⊖
When Order is Hold	4	⊖
When Order is Unhold	5	⊖
When Order is Cancelled	6	⊖
When Order is Invoiced	7	⊖

- This will be used to send SMS from SMS Alert when order is set on HOLD.

5. When Order is Unhold

- This will be used to send SMS from SMS Alert when order is set on UNHOLD.

6. When Order is Cancelled

- This will be used to send SMS from SMS Alert when order is CANCELLED.

7. When Order is Invoiced (Completed)

- This will be used to send SMS from the Voodoo API when order is COMPLETED

8. ENABLE CUSTOMER NOTIFICATIONS

- This will be used to enable the SMS alert it will be available in all tabs

9. Enter SENDER ID

- Sender ID is the name of the sender or the name that appear in FROM of the SMS

A. ENTER THE MESSAGE

The screenshot shows a configuration form for SMS alerts. It includes the following elements:

- 8 Enable Customer Notification:** A dropdown menu set to "Yes". Below it, a note states: "This option will send SMS when an Order is Placed".
- 9 Enter the Sender ID:** A text input field. Below it, a note states: "Company' e.g. My Store' (max: 11 alphanumeric characters. This is who the SMS will appear from when received)".
- A Enter the Message:** A large text area for the message content. Below it, a note states: "Your Message Content, (Max 918 characters. Text over 160 characters may incur multiple credit charges)".
- B (VIEW):** A button to view the message content.
- C:** A button located at the bottom right of the message content area.
- When Order is Hold, When Order is Unhold, When Order is Cancelled:** Three rows, each with a text label and a dropdown menu.

- You can some custom fields to edit the SMS defined below

B. TOOLTIP

- It will show a demo message with the custom fields that you can use in the SMS

C. Allowed Number of Character

- D. Yes the allowed number of character for a single SMS is 160 character for more than 160 character multiple credit will charge

Admin Notifications

- Enable this to send SMS to Admin on Store

E. Admin Mobile Number

- This will be used as destination where SMS will be sent

F. Enter The Message

The screenshot shows the 'Admin Configuration' page with the following sections:

- D Enable Admin Notifications:** A dropdown menu is set to 'Yes'. Below it, a note states: 'This option will send SMS to the admin when an Order is Placed'. A '[STORE VIEW]' link is on the right.
- E Admin Mobile:** An empty text input field. Below it, a note states: 'Admin Mobile(s) (Enter as many numbers as you like Here, comma separated if multiple e.g. 07700900000,07700900001)'. A '[STORE VIEW]' link is on the right.
- F Enter the Message for New Order:** A large empty text area with a help icon. Below it, a note states: 'Your Message Content, (Max 918 characters. Text over 160 characters may incur multiple credit charges)'. A '[STORE VIEW]' link is on the right.
- Enter the Message for Order Hold:** A large empty text area with a help icon. Below it, a note states: 'Your Message Content, (Max 918 characters. Text over 160 characters may incur multiple credit charges)'. A '[STORE VIEW]' link is on the right.

- Enter messages with different custom fields to send on different status

G. Basic Configuration

H. Order Notifications

I. Admin Notifications

- G,H,I are links to the respective pages.