

SendGrid

This extension allows you to configure Magento 2 to send all emails using SendGrid.

Description

SendGrid's cloud-based email infrastructure relieves businesses of the cost and complexity of maintaining custom email systems. SendGrid provides reliable delivery, scalability and real-time analytics along with flexible APIs that make custom integration a breeze.

The SendGrid plugin uses SMTP or API integration to send outgoing emails from your Magento installation.

Configuration

Log into your Magento Admin, then go to System -> SendGrid -> Settings and enter your settings.

- To get the SendGrid plugin running after you have activated it, go to the plugin's settings page and set the SendGrid API Key, then choose how your email will be sent - either through SMTP or API.

Authentication

API Key :

Send Method :

- You can also set default values for the "From Name", "Sending Address" and the "Reply Address", so that you don't need to set these headers every time you want to

send an email from your application.

From Name :

Name as it will appear in recipient clients.

Sending Address :

Email address from which the message will be sent.

Reply Address :

Email address where replies will be returned.

- Emails are tracked and automatically tagged for statistics within the SendGrid Dashboard. You can also add other category for your emails in the field "Categories".

Categories :

Leave blank to send without categories.

Associates the category of the email this should be logged as.

Categories must be separated by commas (Example: category1,category2).

- You can set the template ID to be used in all your emails on the settings page.

Template :

Leave blank to send without template.

The template ID used to send emails.

Example: 0b1240a5-188d-4ea7-93c1-19a7a89466b2.

**Your API Key will need permissions for Read Access to the Template Engine.*

- You can select the unsubscribe group.

Unsubscribe Group :

User will have the option to unsubscribe from the selected group.

**Your API Key will need permissions for Read Access to the Unsubscribe Groups.*

- If you would like to configure categories for statistics, you can configure it by setting the 'Categories' field in the 'Statistics Settings' section

Statistics Settings

Categories :


Leave blank to display only default stats.

Add some categories for which you would like to see your stats.

Categories must be separated by commas (Example: category1,category2).

Statistics

Log into your Magento Admin, then go to System -> SendGrid -> Statistics to see your statistics.



Requirements

- Magento Community Edition 2.x or Magento Enterprise Edition 2.x

Frequently asked questions

What credentials do I need to add on settings page ?

Create a SendGrid account at <https://sendgrid.com/partners/magento/> and generate a new API key on https://app.sendgrid.com/settings/api_keys.

What permissions should my API keys have ?

The API Key needs to have Full Access to Mail Send, Read Access to Stats, Read Access to Template Engine and Read Access to Unsubscribe Groups.