

How to integrate your Magento store with ShipRocket?

Integrate your store with our platform and streamline Magento shipping and order fulfilment process now. Proceed with the following steps to connect your Magento Store with ShipRocket. There are two ways to integrate Magenta with Shiprocket.

- **USING THE MAGENTO ADMIN PANEL**

1. Login to the Magento Admin Panel
2. On the Taskbar, go to System -> Web Services -> SOAP/XML-RPC – Users.
3. Click on {Add New User}
4. Under ‘User Info’ Tab, fill all the required information.
5. Now, click on {Save User}
6. Once more, from the Taskbar, go to System -> Web Services -> SOAP/XML-RPC – Roles
7. Click on {Add New Roles}
8. Select the ‘Role Info’ tab, and input the role name i.e. Superadmin.
9. Click on the ‘Role Resources’ tab and select ‘Resource Access – All’ from the drop down menu. Now, click on ‘Save Role’.
10. One last time, from the taskbar go to System - > Web Services -> SOAP/XML-RPC – Users [Or, just repeat step 2].
11. Select the User Name which has been entered in Step 4.
12. Under the ‘User Role’ tab, click on the assigned role name i.e. Superadmin (As in Step 8).
13. Now Click on {Save User}. Congratulations. You successfully integrated your Magento Store with ShipRocket.

- **USING THE SHIPROCKET PANEL**

1. Login to the ShipRocket panel.
2. On the Taskbar, go to Settings -> Channels.
3. Click on {Add New Channel}.
4. From the list of Channels/Stores, select Magento -> Integrate.
5. Switch ‘On’ the Order and Inventory Sync and mention the status of orders on Magento, which is to be fetched in the system.
6. Fill in the parameters saved from the Magento Panel
Store URL: The URL of your online store.
API Key and API Username: API details of your Magento Panel (as mentioned in Step 4).
7. Click on ‘Save Channel & Test Connection’.
8. The Green Icon indicates that the channel has been successfully configured.
Congratulations. You successfully integrated your Magento Store with ShipRocket.